

TeamSpeak 3 (1)

Configuring the connection between GSManager and a [Teamspeak3](#) server.

If you want to connect the GSManager to your own [TeamSpeak 3](#) server, you must configure it accordingly. In the [basics.json](#), you can find the following section:

JavaScript

```
"teamspeak3" : {  
  
    },
```

<u>Variable</u>	<u>Allowed Values</u>	<u>Description</u>
enabled	true/false	Should the GSManager connect to your TS3 -Server, then set to true. If you don't want to use the TS3 features, then set to false.
ip	String	The IP of the TS3 -Server.
password	String	The password of the ServerQuery user (more about this below in the section TS3-ServerQuery).
serverqueryport	Number	The TCP-Port of the ServerQuery.
username	String	The Username of the ServerQuery User.
voiceport	Number	The TS3 -Port, which you are using to connect to your TS3 -Application.

[TS3-ServerQuery](#)

Please be patient, that we are only providing basic information about the TS ServerQuery, which are actually the most important information to connect your GSManager to your [TS3](#)-Server (Further information may be delivered, if needed)

Add a ServerQuery User:

You can add a Username in your [TS3](#) by clicking on Extras -> ServerQuery Login. A password will be set automatically. You must add these two information in the configuration above.

Which TS3-Permissions?

To add a ServerQuery User you require the permission `b_client_create_modify_serverquery_login`. It depends how your [TS3](#)-Server was configured by default, your ServerQuery User requires further permissions (for sending textmessages, poking, receiving the list about each connected [TS3](#)-Client, etc.). If a required permission is not given, you will find any information about this in the GSManager logfile.

Whitelist:

Each [TS3](#)-Server has his own "flood protection" equipped, which prevents spam to a [TS3](#)-Server. By a basic configuration, any user (even your ServerQuery User) is only allowed to perform 10 commands in 3 seconds. This should also be enough for the GSManager, but by increased number of players and thus also potentially higher communication to the [TS3](#)-Server. this could result in a bottleneck. There is a `query_ip_whitelist.txt` in the [TS3](#)-Server directory, which prevents this. By adding the IP-adress of the GSManager, it is allowed to perform commands without any limitations. In case your [TS3](#)-Server and your GSManager are running on the same system, the you can also use the IP `127.0.0.1` (must be entered

in `basics.json` -> `teamspeak3` -> `ip`), which has been added to the Whitelist (by default of [TS3](#)).